

Pegasus Mail is a free, standards-based electronic mail client suitable for use by single or multiple users on single computers or on local area networks. This is the mailer UUPlus recommends for Outlook users who cannot get Outlook to work. Pegasus Mail has the unique ability to directly access inbound mail and send outbound mail without using the POP or SMTP servers.

Installing Pegasus Mail for use with the UUPlus POP and SMTP servers:

1. Place the UUPlus CD in the CD-ROM.
2. When the UUPlus installation menu appears, select Available Mailers and then double click the Pegasus Mail executable.
3. The Pegasus Mail Self-Extractor will appear. Click [**Setup**] to run the install program.
4. The Pegasus Mail welcome window will appear. Click [**Next**] to begin the installation process.
5. Install Pegasus Mail in the location "C:\pmail" and click [**Next**].
6. Check the boxes for "Start menu" links and "web mailto:" links and click [**Next**].
7. Click [**Finish**] to install Pegasus Mail on your computer.
8. Pegasus Mail will be copied onto your computer. When it is finished, click [**Exit**].
9. The Pegasus Mail icon should appear on your Desktop. Double-click the Pegasus Mail icon to run Pegasus Mail.
10. Pegasus Mail will ask you how you want your account configured. Select the "Single User" option (top).
11. Pegasus Mail will not ask where to install your mailbox. I recommend using "C:\PMAIL\MAIL." It will make Pegasus Mail happier.
12. Pegasus Mail will open the Internet wizard. Click [**Next**] to configure your account.
13. Type in your UUPlus email address and click [**Next**].
14. Type "localhost" as the address of your POP3 server and click [**Next**].
15. Type in your UUPlus account name and password. Your account name is what precedes the "@" symbol in your email address. Click [**Next**] to continue.
16. Type "localhost" as the address of your SMTP server and click [Next] to continue. Pegasus Mail should correctly guess the address.
17. Select "Network" and click [**Next**].
18. Your account is now configured; click [Finish] to save the account.
19. To send and receive your mail from UUPlus, click the globe icon with the red and blue arrows.

If Pegasus Mail reports the error that it is unable to connect to the host when you try popping your mail in UUPlus Personal, the most likely reason is that the port 110, which is used by the mailer and UUPlus Personal to communicate, is blocked. The port is being blocked by third-party software, probably a virus scanner. The solution is to change the port being used by Personal and your mailer.

UUPlus:

1. Open UUPlus Personal.
2. Select [**Setup**].
3. On the General Tab, find "Local Mail Server Ports."
4. Change POP from 110 to 109.
5. Change SMTP from 25 to 24.
6. Click [**Done**].
7. Shutdown Personal and restart the program.

Pegasus Mail

1. Open Pegasus Mail.
2. Select [**Tools — Internet Options**].
3. Select the Receiving (POP3) tab.
4. Under "Advanced POP3 settings," change the TCP/IP port from 110 to 109.
5. Select the Sending (SMTP) tab.
6. Under "Advanced SMTP settings," change the TCP/IP port from 25 to 24.
7. Click [**OK**] to save your changes.

Now try popping your mail. You will know it works if your inbound mail from Personal arrives in your new mail folder and your outbound mail is no longer in the queue. Also, if no errors appear then everything should be working.

User-Defined Gateway:

This mode will not work with Windows XP. Windows XP cannot run DOS programs.

If you have been unable to get any mailer to access your mail, Pegasus Mail can be configured to send and receive email directly from UUPlus software without going through the POP and SMTP servers. This configuration requires the use of a DOS program. Please follow these instructions precisely.

Installing Pegasus Mail in User-Defined Gateway Mode:

If you have already installed Pegasus Mail, uninstall Pegasus Mail and start from the beginning.

1. Place the UUPlus CD in the CD-ROM.
2. When the UUPlus installation menu appears, select Pegasus Mail.
3. The Pegasus Mail Self-Extractor will appear. Click [**Setup**] to run the install program.
4. The Pegasus Mail welcome window will appear. Click [**Next**] to begin the installation process.
5. Install Pegasus Mail in the location "C:\mail" and click [**Next**].
6. Check the boxes for "Start menu" links and "web mailto:" links and click [**Next**].
7. Click [**Finish**] to install Pegasus Mail on your computer.
8. Pegasus Mail will be copied onto your computer. When it is finished, click [**Exit**].
9. Open UUPlus Personal.
10. Select [**Setup**].
11. On the General tab, find and check the box labeled "Disable Pop and SMTP Servers." By checking this, you are turning off the POP and SMTP servers, which are not needed in the User-Defined Gateway mode. If the POP and SMTP servers are not turned off, then unused command files will be created and may cause problems in the operation of the software.
12. Click [**Done**] and restart UUPlus Personal. You will notice the POP and SMTP servers did not start.
13. Open Pegasus Mail. There should be a shortcut on your desktop.
14. Pegasus Mail will ask you how you want your account configured. Select the "Single User" option (top).
15. Pegasus Mail will ask where to install your mailbox, I recommend using "C:\MAIL\MAIL." It will make Pegasus Mail much happier.
16. Pegasus Mail will open and start the Internet Setup Wizard. Click [**Cancel**], we do not want to configure the Internet Wizard. Click [**OK**] to confirm that you want to cancel. You will not be using the POP and SMTP server to access your mail and therefore you do not need the Internet Wizard.
17. On the menu bar select [**Tools — Options**].
18. This is where you will do a lot of customization and configuration of Pegasus Mail mailer. For now, select the "Advance Settings" section under the "General Settings." At the bottom change the "Load Windows Internet Services" from "On demand only" to "Never." This will prevent Pegasus Mail from looking for the POP and SMTP servers.
19. Click [**Apply**] to save settings and [**OK**] exit out of "Options."
20. On the menu bar, select [**File — Exit**] to close out of Pegasus Mail.
21. Click the [**Start**] button and select [Run]. On the "Open" line type "c:\mail\p conf ig.exe" and click [**OK**].
22. A DOS program called "Pegasus Mail Configuration" will open. This program can only be used with arrow keys and the keyboard. The mouse is useless in this program. Scroll down with the arrow keys to "Manage user-defined gateways" and hit the [**Enter**] key.
23. A box labeled "Defined Gateways" will appear. To define a new gateway, press the [**Ins**] (Insert) key.
24. Below is a replication of what information needs to be entered to define the gateway. On the second line, substitute "...username" with your username. Substitute username@uuplus.com for your email address. If your username contains non-standard characters such as periods or dashes, do not include these non-standard characters in the username. For example, the username John.Smith will use the path "c:\uuplus\spool\mail\johnsmith." It is all right to include the non-standard characters on the "Reply address format." Type in the information and press "Enter" to go to the next line. At the end, you will be asked to accept this data, if everything is entered correctly, press "Y", otherwise press "N."